


Boulder Voices for Children – SSL-VPN Setup Instructions


1. Open a web browser and go to <https://www.sonicwall.com/products/remote-access/vpn-clients/>. Click on the Download button under the appropriate operating system, then run the file after it has downloaded.
2. Click NEXT at the beginning of the Setup Wizard (this install process will only need to be done once)




3. Click "I Agree" then click NEXT




4. Leave the install folder as the default value, then click NEXT




5. Enter the Default Server: 23.24.149.186:4433 and Default Domain: LocalDomain, then click NEXT



6. Then click NEXT to have the system add shortcuts for later access




7. After installation, click Close.




After install, reboot the computer! This is important as it may not ask and maybe necessary before the program will function properly.

8. When connecting to the server, use the following (Your Manager will have the password), then click CONNECT
Verify the address is **23.24.149.186:4433**, enter sslvpn and your password, and the domain is **LocalDomain**.




The screenshot shows the SonicWall NetExtender application window. At the top, the title bar reads "NetExtender". Below the title bar, the SonicWall logo and "NetExtender" text are displayed. The main area contains a login form with the following fields: "Server:" with a dropdown menu showing "23.24.149.186:4433", "Username:" with a text box containing "sslvpn", "Password:" with a masked text box (dots), and "Domain:" with a text box containing "LocalDomain". A "Connect" button is located below the domain field. At the bottom of the form area, there is a checkbox labeled "Always ask for user name & password" which is currently checked. The bottom status bar includes icons for help, settings, and information, along with the copyright notice "© 2022 SonicWall Inc."

9. Click "Always Trust" to the Certificate screen



The screenshot shows a Windows Security Alert dialog box. The title bar reads "Security Alert". The main text states: "Information you exchange with this site cannot be viewed or changed by others. However, there is a problem with the site's security certificate." Below this, there are three bullet points: a warning icon followed by "The security certificate was issued by a company you have not chosen to trust. View the certificate to determine whether you want to trust the certifying authority.", a checkmark icon followed by "The security certificate date is valid.", and a warning icon followed by "The name on the security certificate is invalid or does not match the name of the site". At the bottom, it asks "Do you want to proceed?". There are four buttons: "Accept", "Cancel", "Always Trust" (which is highlighted with a red rectangle), and "View Certificate".

10. After the reboot from the first install, you should now be able to connect. To disconnect the session, click the “Disconnect” button. During your session, you can minimize this screen while you work.



11. After the VPN connection has been established, you can open an RDP connection to any PC connect to the Network or access any file shares on the laptop.

